



Einbindung von De-Mail in NoSpamProxy

Version 15

Legal information

All rights reserved. This document and the applications described therein are copyrighted products of Net at Work GmbH, Paderborn, Federal Republic of Germany. This document is subject to change without notice. The information contained in this document does not constitute an assumption of warranty or liability on the part of Net at Work GmbH. The partial or complete reproduction is only permitted with the written permission of Net at Work GmbH.

Copyright © 2023 Net at Work GmbH

Net at Work GmbH
Am Hoppenhof 32a
D-33104 Paderborn
Germany

Microsoft®, Windows®, Microsoft Exchange®, SQL Server®, SQL Server Express®, Windows Server 2008®, Windows Server 2012®, Windows Server 2012 R2®, Windows Server 2016®, Microsoft .NET Framework®, Microsoft Report Viewer®, Microsoft Office®, Microsoft 365®, Office 365®, Microsoft Outlook®, Microsoft Visual Studio® and Azure® are registered trademarks of Microsoft Corporation. NoSpamProxy® and 32Guards® are registered trademarks of Net at Work GmbH. All other trademarks used belong to the respective manufacturers or owners.

THIS DOCUMENT WAS LAST EDITED ON DECEMBER 11, 2024.

Content

Requirements	1
Installation	3
Notes on using USB servers	3
Smartcard	3
Configuration	6
Registering certificates	6
Promoting certificates	7
Configuring the De-Mail connection in NoSpamProxy	8
Configuring the connection to T-Systems De-Mail	8
Creating connectors for De-Mail	9
Help and support	12

Requirements

To connect to the De-Mail infrastructure and use a De-Mail address from T-Systems in NoSpamProxy, you need

- a smart card,
- a smartcard reader and
- the TeleSec Card Management Tool.

Smartcards are used to store the cryptographic key material and the certificates. Telekom SmartCards work on the basis of the TeleSec Chipcard Operating System (TCOS). This is also able to calculate the cryptographic algorithm within the chip and thus securely store keys. It is a chip card that is read by means of a card reader - the SmartCard Reader.

Smartcard readers read the smartcards, but also establish the connection to the Gateway Role. Special software is required to manage the smartcard, with which you can change PINs or load certificates or keys onto your smartcard, for example. You can also access detailed information about your smart card, such as the card type, the card number or the amount of memory still available. The **TeleSec Card Management Tool** is a software that has been specially developed for use with T-Systems De-Mail interfaces.



NOTE: If you operate the smartcard reader within a virtualized server infrastructure, you have to integrate it with the help of a USB server.



NOTE: Since the PIN is used by the software, no reader with its own keyboard may be used.



NOTE: Each gateway server requires its own card reader and a dedicated smart card.

Installation



NOTE: You must install all smart card components from the server console. Installation via a remote desktop connection will result in an incorrect installation.

Notes on using USB servers

- Make sure that you use a dedicated and permanently configured IP address (no DHCP) for the USB server.
- Be sure to include the USB ports in the guest system.
- To have the USB server automatically connected when the operating system starts, you must add the USB server integration to the autostart list.

Smartcard

Installing the smartcard driver

To access the smartcard, first install the driver for the TCOS (TeleSec Chipcard Operating System). Use the TCOS card module driver for manual installation.

1. Download the [TCOS card module driver](#).
2. Unpack the ZIP archive.
3. Install the driver.



NOTE: After installation, make sure that the smart card is visible in the Device Manager and is shown as correctly installed.

Installation of the TCOS Cardmanager

Now install the Cardmanager software as follows

1. Download the TeleSec Cardmanager .
2. Unpack the ZIP archive.
3. Install the software.

Configuration

Now register the certificates on your server and make them available for use in the server's certificate store.



NOTE: The configuration steps described here must be performed from the server console. It is not possible to do it via remote desktop connection.

Proceed as follows:

■ Registering certificates

1. Start the Telesec Card Manager.
2. Go to **Personalization > Certificates**.
3. Select the corresponding certificates.
4. Open the drop-down menu **Certificate**.
5. Select **Register**.
6. Enter the smartcard PIN and click **OK**.
7. Restart the server.

I Promoting certificates

You must now promote the registered certificates to the local certificate store so that the software can work with the certificates. To do this, you need the **CertificatePromoter.exe** application, which you can obtain from [NoSpamProxy Support](#).

Proceed as follows:

1. Start the **CertificatePromoter.exe**.
2. Highlight the registered certificates.
3. Click **OK**.
4. Restart the server.



NOTE: Make sure that the certificate store contains at least the certificate for Client Authentication and Smart Card Logon.

Configuring the De-Mail connection in NoSpamProxy

Now configure

- the connections to the service provider T-Systems and
- the connectors required for De-Mail.

I Configuring the connection to T-Systems De-Mail

To create connectors for De-Mail via T-Systems, you have to configure the connections to the service provider.

Proceed as follows:

1. In the NoSpamProxy Command Center, go to **Configuration > Connected systems > De-Mail providers**.
2. Click **Add**.
3. Enter a name for the connection and select **T-Systems** as the target.
4. Select the certificate to be used and enter your certificate PIN.
5. Click **Save and Close**.

Telekom De-Mail-Verbindung

Bitte wählen Sie aus, welches Telekom De-Mail-Gateway Sie verwenden möchten.

Name

Ziel T-Deutschland T-Systems

Zertifikat Kein Zertifikat ausgewählt.

Zertifikats-PIN



NOTE: By selecting the certificate, the profile is automatically bound to a Gateway Role. Connectors that use the profile are automatically assigned to the Gateway Role on which the certificate resides.


Creating connectors for De-Mail

Now create an outbound send connector that will be used for sending emails over De-Mail connections.


Proceed as follows:

1. In the NoSpamProxy Command Center, go to **Configuration > Email routing > Outbound send connectors**.
2. Select **Add**.


3. In the dialog box, select **De-Mail via Telekom** as the outbound send connector and click **Next**.




4. Enter a name for the connector and select the provider from the drop-down list.



5. Click **Add** in the next dialog box to assign a domain to the connector.



6. In the **Available corporate domains** dialog box, select the desired domain and click **Save and close**.



7. Click **Finish**.

Help and support

Knowledge Base

The [Knowledge Base](#) contains further technical information on various problems.

Website

The [NoSpamProxy website](#) contains manuals, white papers, brochures and other information about NoSpamProxy.

NoSpamProxy Forum

The [NoSpamProxy forum](#) gives you the opportunity to exchange information with other NoSpamProxy users, get tips and tricks and share them with others.

Blog

The [blog](#) offers technical support, tips on new product versions, suggestions for changes to your configuration, warnings about compatibility problems and much more. The latest news from the blog is also displayed on the start page of the NoSpamProxy Command Center.

YouTube

On our [YouTube](#) channel you will find tutorials, how-tos and other product information that will make working with NoSpamProxy easier.

NoSpamProxy Support

You can reach our support team

- by phone at [+49 5251304-636](tel:+495251304636)
- by email at support@nospamproxy.de.

